

9000M2 Series Mixer/Amplifiers RS-232C Protocol Manual

Ver.2.00A 2011/11/30

TABL	E OF	CONTENTS	Page#
1.	SU	MMARY	3
2.	SE	RIAL PORT SETTING	4
3.	CO	MMAND CONFIGURATION	4
4.	TR	ANSMISSION DATA AFTER COMMAND RECEPTION	4
5.	CO	NTROL COMMAND AND SETTING VALUE	5
5.1	. c	hannel Fader Gain	5
5	5.1.1.	Channel Fader Gain - Position setting	5
5	5.1.2.	Channel Fader Gain(Paging Output Volume) - Position setting	7
5	5.1.3.	Channel Fader Gain - Step Up/ Step Down	9
5.2	. C	Prosspoint Gain	11
5.3	. Р	reset Memory Recall	13
5.4	. C	Channel ON/OFF	14
5.5	. Р	ower ON/OFF	14
5.6	. т	one Control	15
5.7	. E	Q Settings	17
5.8	. L	oudness Compensation Settings	19
5.9	. F	ilter Settings	20
5.1	0. Ir	nput Sensitivity Setting	21
5.1	1. P	hantom Power ON/OFF Setting	22
5.1	2. P	aging Event Preset Recall	23
6.	Ch	annel Name Request	24
7.	Sp	eaker Preset Setting	25
8.	AN	C ADJUST	26
8.1	. А	NC Adjust Setting	26
8.2	. A	NC Get Reference	28
9.	CO	MMAND LIST	30
10	CO	MMINICATION EYAMDI ES	22

1. SUMMARY

The RS-232C protocol described in this document is designed to be used to control the 9000M2 Series Amplifier from a PC and/or remote controller. This specification applies to the 9000M2 Series firmware version 1.00 or later.

There are both descriptions of mixer mode and matrix mode in this manual, but only mixer mode available with 9000M2 series.

Settings that can be controlled are as follows:

- Channel Fader Gain
- Crosspoint Gain
- Preset Memory Recall
- · Channel ON/OFF
- Power ON/OFF
- Tone Control
- EQ Settings(ON/OFF, Band number selection, Gain setting, Q setting, Center frequency setting)
- Loudness Compensation Settings
- Filter Settings(High Pass Filter/Low Pass Filter)
- Filter Settings
- Input Sensitivity Setting
- · Phantom Power ON/OFF Setting
- Paging Event Preset Recall

Following values can be read from the 9000M2 Series Amplifier.

Channel name

When connecting the PC and/or remote controller to the 9000M2 Series Amplifier using this protocol, set the 9000M2 Series Amplifier's RS-232C port as follows:

Bit rate: 9,600/19,200/38,400/57,600 bps (Select the band rate depending on the remote controller to be connected.) (See; Operating instructions of the 9000M2 Series Amplifiers.)

COMMANDLIST, COMMUNICATION EXAMPLES and PARAMETER TABLES are available at the end of each section of this document.

2. SERIAL PORT SETTING

- 9,600/19,200/38,400/57,600 bps, 8 bits, non-parity, stop bit: 1, non flow control
- · Connector: D-sub 9 pins, straight cable
- Signal line: No.2=TX, No.3=RX, No.5=Ground

3. COMMAND CONFIGURATION

•	Command	Data length (N)	Data 1	Data 2	Da	ta N	
•	Command] is in the range of 8	30H to FFH.	D	ata length	ar	re in the
	Data ra	nge of 00H to 7FH.				_	

- Data length (N) refers to the length of the subsequent data of Data 1 to Data N.
- If received data contains more byte data than the Data length, these exceeding data are abandoned.
- If a next command received contains byte data shorter than the Data length, the previous command is abandoned.

4. TRANSMISSION DATA AFTER COMMAND RECEPTION

When normal data is received, the same data as the reception data is to be transmitted. Example: 91H, 03H, 00H, 00H, 00H (Reception data)

→ 91H, 03H, 00H, 00H, 00H (Transmission data)

When channel data is received and the data is outside of the range, the data is to be inverted and transmitted.

Example: 91H, 03H, 00H, <u>08H</u>, 00H (Reception data)

→ 91H, 03H, 00H, 77H, 00H (Transmission data)

When abnormal data is received, the data is to be inverted and transmitted.

Example: 91H, 03H, 00H, 00H, 6AH (Reception data)

→ 91H, 03H, 00H, 00H, 15H (Transmission data)

When data other than channel data is received and the data is outside of the range, no data is transmitted.

Example: 91H, 03H, 05H, 00H, 6AH (Reception data)

→ No response

See section 9. COMMUNICATION EXAMPLES for other transmission data when normal data is received.

5. CONTROL COMMAND AND SETTING VALUE

5.1. Channel Fader Gain

5.1.1. Channel Fader Gain - Position setting

Set the input and output channel fader gains to a fixed value position.

Note: Command cannot be received during power off.

9000M2 Series Amplifier responds with the same data as that received.

91H, 03H, <Channel Attribute>, <Channel Number>, <Value>

<Channel Attribute>
00H: Input channel
01H: Output channel

<Channel Number>
00H - 07H (Input channel 1 - 8)
00H - 07H (Output channel 1 - 8)

<Value>
Position setting

 $00 - 7EH (-\infty \text{ to } +10 \text{ dB})$

See Channel Fader Gain - Position V/S Gain Table on the next page.

Example: Setting the fader gain of channel 1 to 0 dB 91H, 03H, 00H, 00H, 6AH

CHANNEL FADER GAIN - POSITION V/S GAIN TABLE

Pos	ition	Gain									
HEX	DEC	(dB)									
00H	0	_∞	22H	34	-36.0	44H	68	-19.0	66H	102	-2.0
01H	1	-70.0	23H	35	-35.5	45H	69	-18.5	67H	103	-1.5
02H	2	-68.0	24H	36	-35.0	46H	70	-18.0	68H	104	-1.0
03H	3	-66.0	25H	37	-34.5	47H	71	-17.5	69H	105	-0.5
04H	4	-64.0	26H	38	-34.0	48H	72	-17.0	6AH	106	0.0
05H	5	-62.0	27H	39	-33.5	49H	73	-16.5	6BH	107	+0.5
06H	6	-60.0	28H	40	-33.0	4AH	74	-16.0	6CH	108	+1.0
07H	7	-59.0	29H	41	-32.5	4BH	75	-15.5	6DH	109	+1.5
08H	8	-58.0	2AH	42	-32.0	4CH	76	-15.0	6EH	110	+2.0
09H	9	-57.0	2BH	43	-31.5	4DH	77	-14.5	6FH	111	+2.5
0AH	10	-56.0	2CH	44	-31.0	4EH	78	-14.0	70H	112	+3.0
0BH	11	-55.0	2DH	45	-30.5	4FH	79	-13.5	71H	113	+3.5
0CH	12	-54.0	2EH	46	-30.0	50H	80	-13.0	72H	114	+4.0
0DH	13	-53.0	2FH	47	-29.5	51H	81	-12.5	73H	115	+4.5
0EH	14	-52.0	30H	48	-29.0	52H	82	-12.0	74H	116	+5.0
0FH	15	-51.0	31H	49	-28.5	53H	83	-11.5	75H	117	+5.5
10H	16	-50.0	32H	50	-28.0	54H	84	-11.0	76H	118	+6.0
11H	17	-49.0	33H	51	-27.5	55H	85	-10.5	77H	119	+6.5
12H	18	-48.0	34H	52	-27.0	56H	86	-10.0	78H	120	+7.0
13H	19	-47.0	35H	53	-26.5	57H	87	-9.5	79H	121	+7.5
14H	20	-46.0	36H	54	-26.0	58H	88	-9.0	7AH	122	+8.0
15H	21	-45.0	37H	55	-25.5	59H	89	-8.5	7BH	123	+8.5
16H	22	-44.0	38H	56	-25.0	5AH	90	-8.0	7CH	124	+9.0
17H	23	-43.0	39H	57	-24.5	5BH	91	-7.5	7DH	125	+9.5
18H	24	-42.0	3AH	58	-24.0	5CH	92	-7.0	7EH	126	+10.0
19H	25	-41.0	3BH	59	-23.5	5DH	93	-6.5			
1AH	26	-40.0	3CH	60	-23.0	5EH	94	-6.0			
1BH	27	-39.5	3DH	61	-22.5	5FH	95	-5.5			
1CH	28	-39.0	3EH	62	-22.0	60H	96	-5.0			
1DH	29	-38.5	3FH	63	-21.5	61H	97	-4.5			
1EH	30	-38.0	40H	64	-21.0	62H	98	-4.0			
1FH	31	-37.5	41H	65	-20.5	63H	99	-3.5			
20H	32	-37.0	42H	66	-20.0	64H	100	-3.0			
21H	33	-36.5	43H	67	-19.5	65H	101	-2.5			

5.1.2. Channel Fader Gain(Paging Output Volume) - Position setting

Set the Paging output volume channel fader gains to a fixed value position.

Note: Command cannot be received during power off.

9000M2 Series Amplifier responds with the same data as that received.

96H, 03H, <Channel Attribute>, <Channel Number>, <Value>

<Channel Attribute> 01H: Output channel

<Channel Number>
00H - 07H (Paging Output channel 1 - 8)

<Value>
Position setting

00 - 7EH (- ∞ to +10 dB)

See CHANNEL FADER GAIN(Paging Output Volume) - POSITION V/S GAIN TABLE on the next page.

Example: Setting the fader gain of channel 1 to 0 dB 96H, 03H, 01H, 00H, 6AH

CHANNEL FADER GAIN(Paging Output Volume) - POSITION V/S GAIN TABLE

CITAL	AIAFF	FADER	GAIN	rayıı	ig Outpu	it voi	ume) ·	- PUSITI	ON V	3 GA	IN IADL
Pos	ition	Gain	Pos	ition	Gain	Pos	ition	Gain	Pos	ition	Gain
HEX	DEC	(dB)	HEX	DEC	(dB)	HEX	DEC	(dB)	HEX	DEC	(dB)
00H	0	8	22H	34	-36.0	44H	68	-19.0	66H	102	-2.0
01H	1	-70.0	23H	35	-35.5	45H	69	-18.5	67H	103	-1.5
02H	2	-68.0	24H	36	-35.0	46H	70	-18.0	68H	104	-1.0
03H	3	-66.0	25H	37	-34.5	47H	71	-17.5	69H	105	-0.5
04H	4	-64.0	26H	38	-34.0	48H	72	-17.0	6AH	106	0.0
05H	5	-62.0	27H	39	-33.5	49H	73	-16.5	6BH	107	+0.5
06H	6	-60.0	28H	40	-33.0	4AH	74	-16.0	6CH	108	+1.0
07H	7	-59.0	29H	41	-32.5	4BH	75	-15.5	6DH	109	+1.5
08H	8	-58.0	2AH	42	-32.0	4CH	76	-15.0	6EH	110	+2.0
09H	9	-57.0	2BH	43	-31.5	4DH	77	-14.5	6FH	111	+2.5
0AH	10	-56.0	2CH	44	-31.0	4EH	78	-14.0	70H	112	+3.0
0BH	11	-55.0	2DH	45	-30.5	4FH	79	-13.5	71H	113	+3.5
0CH	12	-54.0	2EH	46	-30.0	50H	80	-13.0	72H	114	+4.0
0DH	13	-53.0	2FH	47	-29.5	51H	81	-12.5	73H	115	+4.5
0EH	14	-52.0	30H	48	-29.0	52H	82	-12.0	74H	116	+5.0
0FH	15	-51.0	31H	49	-28.5	53H	83	-11.5	75H	117	+5.5
10H	16	-50.0	32H	50	-28.0	54H	84	-11.0	76H	118	+6.0
11H	17	-49.0	33H	51	-27.5	55H	85	-10.5	77H	119	+6.5
12H	18	-48.0	34H	52	-27.0	56H	86	-10.0	78H	120	+7.0
13H	19	-47.0	35H	53	-26.5	57H	87	-9.5	79H	121	+7.5
14H	20	-46.0	36H	54	-26.0	58H	88	-9.0	7AH	122	+8.0
15H	21	-45.0	37H	55	-25.5	59H	89	-8.5	7BH	123	+8.5
16H	22	-44.0	38H	56	-25.0	5AH	90	-8.0	7CH	124	+9.0
17H	23	-43.0	39H	57	-24.5	5BH	91	-7.5	7DH	125	+9.5
18H	24	-42.0	3AH	58	-24.0	5CH	92	-7.0	7EH	126	+10.0
19H	25	-41.0	3BH	59	-23.5	5DH	93	-6.5			
1AH	26	-40.0	3CH	60	-23.0	5EH	94	-6.0			
1BH	27	-39.5	3DH	61	-22.5	5FH	95	-5.5			
1CH	28	-39.0	3EH	62	-22.0	60H	96	-5.0			
1DH	29	-38.5	3FH	63	-21.5	61H	97	-4.5			
1EH	30	-38.0	40H	64	-21.0	62H	98	-4.0			
1FH	31	-37.5	41H	65	-20.5	63H	99	-3.5			
20H	32	-37.0	42H	66	-20.0	64H	100	-3.0			
21H	33	-36.5	43H	67	-19.5	65H	101	-2.5			

5.1.3. Channel Fader Gain - Step Up/ Step Down

Set the input and output channel gain positions by the number of steps. Positions can be varied from the current status by the designated number of steps. One position varies per step.

9000M2 series Amplifier informs position values changed by commands. Position values are shown in POSITION V/S GAIN TABLE. Values are 1dB step under -40dB, and 2dB step under -60dB.

The 9000M2 series Amplifier informs position values changed by Step Up or Down. 93H, 03H, <Channel Attribute>, <Channel Number>, <Step>

<Channel Attribute>
00H: Input channel
01H: Output channel

<Channel Number>
00H - 07H (Input channel 1 – 8)
00H - 07H (Output channel 1 – 8)

<Step>

UP: 41H – 5FH (1 – 31 step up); Example showing 0.5dB Step Up: 41H Down: 61H - 7FH (1 – 31 step down); Example showing 0.5dB Step Down: 61H

Example showing 0.5dB up of Input Channel 1 fader gain 93H, 03H, 00H, 00H, 41H

Example of 9000M2 series Amplifier response of +1dB Input Channel 1 fader gain after 0.5dB up.

93H, 03H, 00H, 00H, 6CH

See Channel Fader Gain – Step Up / Step Down Table on the next page.

CHANNEL FADER GAIN - STEP UP / STEP DOWN TABLE

Step	Up	Coin (dD)	Step	Down	Coin (dD)
HEX	DEC	Gain (dB)	HEX	DEC	Gain (dB)
41H	65	+0.5 step	61H	97	-0.5 step
42H	66	+1.0 step	62H	98	-1.0 step
43H	67	+1.5 step	63H	99	-1.5 step
44H	68	+2.0 step	64H	100	-2.0 step
45H	69	+2.5 step	65H	101	-2.5 step
46H	70	+3.0 step	66H	102	-3.0 step
47H	71	+3.5 step	67H	103	-3.5 step
48H	72	+4.0 step	68H	104	-4.0 step
49H	73	+4.5 step	69H	105	-4.5 step
4AH	74	+5.0 step	6AH	106	-5.0 step
4BH	75	+5.5 step	6BH	107	-5.5 step
4CH	76	+6.0 step	6CH	108	-6.0 step
4DH	77	+6.5 step	6DH	109	-6.5 step
4EH	78	+7.0 step	6EH	110	-7.0 step
4FH	79	+7.5 step	6FH	111	-7.5 step
50H	80	+8.0 step	70H	112	-8.0 step
51H	81	+8.5 step	71H	113	-8.5 step
52H	82	+9.0 step	72H	114	-9.0 step
53H	83	+9.5 step	73H	115	-9.5 step
54H	84	+10.0 step	74H	116	-10.0 step
55H	85	+10.5 step	75H	117	-10.5 step
56H	86	+11.0 step	76H	118	-11.0 step
57H	87	+11.5 step	77H	119	-11.5 step
58H	88	+12.0 step	78H	120	-12.0 step
59H	89	+12.5 step	79H	121	-12.5 step
5AH	90	+13.0 step	7AH	122	-13.0 step
5BH	91	+13.5 step	7BH	123	-13.5 step
5CH	92	+14.0 step	7CH	124	-14.0 step
5DH	93	+14.5 step	7DH	125	-14.5 step
5EH	94	+15.0 step	7EH	126	-15.0 step
5FH	95	+15.5 step	7FH	127	-15.5 step

5.2. Crosspoint Gain

Set the crosspoint switch gain. 9000M2 Series Amplifier responds with the same data as that received.

Note: Command cannot be received during power off.

95H, 05H, <Source Channel Attribute>, <Source Channel Number>, <Destination Channel Attribute>, <Destination Channel Number>, <Value>

<Source Channel Attribute> 00H: Input channel

<Source Channel Number> 00H - 07H (Input channel 1 - 8)

<Destination Channel Attribute> 01H: Output channel

<Destination Channel Number> 00H – 07H (Output channel 1 - 8)

<Value>

00 - 51H: Gain Position (-∞ to +10.0 dB)

60 - 6FH: Position Down (1 – 16dB Step Down)

70 - 7FH: Position Up (1 – 16dB Step Up)

Example 1: Setting the crosspoint gain from Input Channel 1 to Output Channel 1 to a fixed value of 0 dB 95H, 05H, 00H, 00H, 01H, 00H, 47H

Example 2: Increasing the crosspoint gain from Input Channel 1 to Output Channel 1 by +3.0 dB steps 95H, 05H, 00H, 00H, 01H, 00H, 72H

See Crosspoint Gain Table on the next page.

CROSSPOINT GAIN TABLE

val	ue	Gain	Va	lue	0 : (15)	Va	lue	0 : (15)	Va	lue	0. 5
HEX	DEC	(dB)	HEX	DEC	Gain (dB)	HEX	DEC	Gain (dB)	HEX	DEC	Step Down
00H	0	_∞	22H	34	-37.0	44H	68	-3.0	65H	101	-6.0 step
01H	1	-70.0	23H	35	-36.0	45H	69	-2.0	66H	102	-7.0 step
02H	2	-69.0	24H	36	-35.0	46H	70	-1.0	67H	103	-8.0 step
03H	3	-68.0	25H	37	-34.0	47H	71	0.0	68H	104	-9.0 step
04H	4	-67.0	26H	38	-33.0	48H	72	1.0	69H	105	-10.0 step
05H	5	-66.0	27H	39	-32.0	49H	73	2.0	6AH	106	-11.0 step
06H	6	-65.0	28H	40	-31.0	4AH	74	3.0	6BH	107	-12.0 step
07H	7	-64.0	29H	41	-30.0	4BH	75	4.0	6CH	108	-13.0 step
08H	8	-63.0	2AH	42	-29.0	4CH	76	5.0	6DH	109	-14.0 step
09H	9	-62.0	2BH	43	-28.0	4DH	77	6.0	6EH	110	-15.0 step
0AH	10	-61.0	2CH	44	-27.0	4EH	78	7.0	6FH	111	-16.0 step
0BH	11	-60.0	2DH	45	-26.0	4FH	79	8.0	Va	lue	Step Up
0CH	12	-59.0	2EH	46	-25.0	50H	80	9.0	70H	112	+1.0 step
0DH	13	-58.0	2FH	47	-24.0	51H	81	10.0	71H	113	+2.0 step
0EH	14	-57.0	30H	48	-23.0	52H	82	reserved	72H	114	+3.0 step
0FH	15	-56.0	31H	49	-22.0	53H	83	reserved	73H	115	+4.0 step
10H	16	-55.0	32H	50	-21.0	54H	84	reserved	74H	116	+5.0 step
11H	17	-54.0	33H	51	-20.0	55H	85	reserved	75H	117	+6.0 step
12H	18	-53.0	34H	52	-19.0	56H	86	reserved	76H	118	+7.0 step
13H	19	-52.0	35H	53	-18.0	57H	87	reserved	77H	119	+8.0 step
14H	20	-51.0	36H	54	-17.0	58H	88	reserved	78H	120	+9.0 step
15H	21	-50.0	37H	55	-16.0	59H	89	reserved	79H	121	+10.0 step
16H	22	-49.0	38H	56	-15.0	5AH	90	reserved	7AH	122	+11.0 step
17H	23	-48.0	39H	57	-14.0	5BH	91	reserved	7BH	123	+12.0 step
18H	24	-47.0	3AH	58	-13.0	5CH	92	reserved	7CH	124	+13.0 step
19H	25	-46.0	3BH	59	-12.0	5DH	93	reserved	7DH	125	+14.0 step
1AH	26	-45.0	3CH	60	-11.0	5EH	94	reserved	7EH	126	+15.0 step
1BH	27	-44.0	3DH	61	-10.0	5FH	95	reserved	7FH	127	+16.0 step
1CH	28	-43.0	3EH	62	-9.0	Va	lue	Step Down			
1DH	29	-42.0	3FH	63	-8.0	60H	96	-1.0 step			
1EH	30	-41.0	40H	64	-7.0	61H	97	-2.0 step			
1FH	31	-40.0	41H	65	-6.0	62H	98	-3.0 step			
20H	32	-39.0	42H	66	-5.0	63H	99	-4.0 step			
21H	33	-38.0	43H	67	-4.0	64H	100	-5.0 step			

5.3. Preset Memory Recall

Recalls any desired preset memories. 9000M2 Series Amplifier responds with the same data as that received.

Note:

Settings to be stored in preset memories are referred to as "SCENE" in mixer mode and "EVENT" in matrix mode.

Preset Memory Recall command cannot be received during power off.

F1H, 02H, 00H, <Preset Number>

<Pre><Pre>et Number> 00H - 1FH: Preset Number 1 - 32

Note: During single channel operation or BGM/PAGE operation in matrix mode 00H - 07H: Preset Number 1 - 8

Example 1: Recalling Preset Memory 1 F1H, 02H, 00H, 00H

Example 2: Recalling Preset Memory 2 F1H, 02H, 00H, 01H

Following command is used to terminate "EVENT" in Matrix Mode. (not available 9000M2 series)

F1H, 02H, 01H, (Event #)

9000M2 series Amplifier ignores this command.

The ROUTE event using the input channel with priority 8 (BGM event) and the BASE event cannot be terminated by this command.

To terminate the BGM event or the BASE event, it is necessary to setup the BGM END event to the unit and activate it.

5.4. Channel ON/OFF

This performs ON/OFF setting of the Input or Output channel. 9000M2 Series Amplifier responds with the same data as that received.

92H, 03H, <Channel Attribute>, <Channel Number>, <ON/OFF>

<Channel Attribute>

00H: Input channel 01H: Output channel

<Channel Number>

00H - 07H (Input channel 1 - 8) 00H - 07H (Output channel 1 - 8)

<ON/OFF>

00H: Channel OFF 01H: Channel ON

Example 1: Setting the Input Channel 1 to ON 92H, 03H, 00H, 00H, 01H

Example 2: Setting the Input Channel 1 to OFF 92H, 03H, 00H, 00H, 00H

5.5. Power ON/OFF

This command performs ON/OFF setting of the power switch of the 9000M2 Series Amplifier. 9000M2 Series Amplifier responds with the same data as that received.

F4H, 01H, <ON/OFF>

<ON/OFF>

00H: Power OFF 01H: Power ON

Example 1: Setting the power switch to OFF. F4H, 01H, 00H

Example 2: Setting the power switch to ON. F4H, 01H, 01H

5.6. Tone Control

Performs Bass and Treble gain settings of the input/output channels. 9000M2 Series Amplifier responds with the same data as that received.

Note: Command cannot be received during power off.

AAH, 04H, <Channel Attribute>, <Channel Number>, <Bass/Treble>, <Value>

<Channel Attribute>

00H: Input channel 01H: Output channel

<Channel Number>

00H - 07H (Input channel 1 - 8) 00H - 07H (Output channel 1 - 8)

<Bass/Treble>

00H: Bass Gain 01H: Treble Gain

<Value>

00 - 18H: Gain Position (-12 to +12dB)

21 - 2CH: Position Down (1 –12dB Step Down)

2D - 38H: Position Up (1 – 12dB Step Up)

Example 1: Setting the Input Channel 1 Bass Gain fixed value to 0 dB. AAH, 04H, 00H, 00H, 00H, 0CH

Example 2: Increasing Input Channel 1 Bass Gain by +3.0 dB step increments. AAH, 04H, 00H, 00H, 00H, 2FH

See Tone Control Gain Position Table on the next page.

TONE CONTROL GAIN POSITION TABLE

| Va | lue | Gain (dB) | Va | lue | Gain (dB) |
|-----|-----|------------|-------|-----|------------|
| HEX | DEC | | HEX | DEC | |
| 00H | 0 | -12.0 | 0DH | 13 | +1.0 |
| 01H | 1 | -11.0 | 0EH | 14 | +2.0 |
| 02H | 2 | -10.0 | 0FH | 15 | +3.0 |
| 03H | 3 | -9.0 | 10H | 16 | +4.0 |
| 04H | 4 | -8.0 | 11H | 17 | +5.0 |
| 05H | 5 | -7.0 | 12H | 18 | +6.0 |
| 06H | 6 | -6.0 | 13H | 19 | +7.0 |
| 07H | 7 | -5.0 | 14H | 20 | +8.0 |
| 08H | 8 | -4.0 | 15H | 21 | +9.0 |
| 09H | 9 | -3.0 | 16H | 22 | +10.0 |
| 0AH | 10 | -2.0 | 17H | 23 | +11.0 |
| 0BH | 11 | -1.0 | 18H | 24 | +12.0 |
| 0CH | 12 | 0 | | | |
| Va | lue | Step Down | Value | | Step Up |
| HEX | DEC | | HEX | DEC | |
| 21H | 33 | -1.0 step | 2DH | 45 | +1.0 step |
| 22H | 34 | -2.0 step | 2EH | 46 | +2.0 step |
| 23H | 35 | -3.0 step | 2FH | 47 | +3.0 step |
| 24H | 36 | -4.0 step | 30H | 48 | +4.0 step |
| 25H | 37 | -5.0 step | 31H | 49 | +5.0 step |
| 26H | 38 | -6.0 step | 32H | 50 | +6.0 step |
| 27H | 39 | -7.0 step | 33H | 51 | +7.0 step |
| 28H | 40 | -8.0 step | 34H | 52 | +8.0 step |
| 29H | 41 | -9.0 step | 35H | 53 | +9.0 step |
| 2AH | 42 | -10.0 step | 36H | 54 | +10.0 step |
| 2BH | 43 | -11.0 step | 37H | 55 | +11.0 step |
| 2CH | 44 | -12.0 step | 38H | 56 | +12.0 step |

Note: 19H – 20H are deemed to be reserved.

5.7. EQ Settings

Perform EQ settings (ON/OFF, Band number, Gain, Q and Center frequency) of the input/output channels. 9000M2 Series Amplifier responds with the same data as that received. Band number, Gain, Q, and Center frequency cannot be received when EQ is set to OFF. They can be valid only when EQ is set to ON.

Note: Command cannot be received during power off.

A1H, 07H, <Channel Attribute>, <Channel Number>, <OFF/ON>, <Band Number>, <Gain Value>, <Q Value>, <Freq Value>

<Channel Attribute>

00H: Input channel 01H: Output channel

<Channel Number>

00H - 07H (Input channel 1 - 8) 00H - 07H (Output channel 1 - 8)

<OFF/ON>

00H: EQ OFF 01H: EQ ON

<Filter Number>

00H - 09H: Filter 01 - 10

<Gain Value>

EQ-GAIN TABLE

| Va | lue | Gain (dB) | Va | lue | Gain (dB) |
|-----|-----|-----------|-----|-----|-----------|
| HEX | DEC | | HEX | DEC | |
| 00H | 0 | -12 | 0DH | 13 | +1 |
| 01H | 1 | -11 | 0EH | 14 | +2 |
| 02H | 2 | -10 | 0FH | 15 | +3 |
| 03H | 3 | -9 | 10H | 16 | +4 |
| 04H | 4 | -8 | 11H | 17 | +5 |
| 05H | 5 | -7 | 12H | 18 | +6 |
| 06H | 6 | -6 | 13H | 19 | +7 |
| 07H | 7 | -5 | 14H | 20 | +8 |
| 08H | 8 | -4 | 15H | 21 | +9 |
| 09H | 9 | -3 | 16H | 22 | +10 |
| 0AH | 10 | -2 | 17H | 23 | +11 |
| 0BH | 11 | -1 | 18H | 24 | +12 |
| 0CH | 12 | 0 | | | |

Note: If testing using Hyperterminal HEX value 0DH may incorrectly translate and will not work. But when used in other applications using the HEX 0DH will work.

<Q Value>

EQ-Q TABLE

| Va | lue | Q |
|-----|-----|-----|
| HEX | DEC | |
| 00H | 0 | 0.3 |
| 01H | 1 | 0.5 |
| 02H | 2 | 0.7 |
| 03H | 3 | 1 |
| 04H | 4 | 1.5 |
| 05H | 5 | 2 |
| 06H | 6 | 3 |
| 07H | 7 | 5 |

<Freq Value>

EQ-FREQUENCY TABLE

| Va | lue | Freq (Hz) | Va | lue | Freq (Hz) |
|-----|-----|-----------|-----|-----|-----------|
| HEX | DEC | | HEX | DEC | |
| 00H | 0 | 20 | 11H | 13 | 1k |
| 01H | 1 | 25 | 12H | 14 | 1.25k |
| 02H | 2 | 31.5 | 13H | 15 | 1.6k |
| 03H | 3 | 40 | 14H | 16 | 2k |
| 04H | 4 | 50 | 15H | 17 | 2.5k |
| 05H | 5 | 63 | 16H | 18 | 3.15k |
| 06H | 6 | 80 | 17H | 19 | 4k |
| 07H | 7 | 100 | 18H | 20 | 5k |
| 08H | 8 | 125 | 19H | 21 | 6.3k |
| 09H | 9 | 160 | 1AH | 22 | 8k |
| 0AH | 10 | 200 | 1BH | 23 | 10k |
| 0BH | 11 | 250 | 1CH | 24 | 12.5k |
| 0CH | 12 | 315 | 1DH | 25 | 16k |
| 0DH | 13 | 400 | 1EH | 26 | 20k |
| 0EH | 14 | 500 | | | |
| 0FH | 15 | 630 | | | |
| 10H | 16 | 800 | | | |

Example: Setting the Input Channel 1's EQ to ON, Band No. to 1, Gain value to +2 dB, Q value to 0.7 and Center frequency to 40 Hz.
A1H, 07H, 00H, 00H, 01H, 00H, 02H, 03H

5.8. Loudness Compensation Settings

Perform loudness compensation settings of the Input / Output channels. 9000M2 Series Amplifier responds with the same data as that received.

Note: Command cannot be received during power off.

ABH, 03H, <Channel Attribute>, <Channel Number>, <OFF/ON>

<Channel Attribute>

00H: Input channel

01H: Output channel

<Channel Number>

00H - 07H (Input channel 1 - 8)

00H - 07H (Output channel 1 - 8)

<OFF/ON>

00H: Loudness OFF

01H: Loudness ON

Example: Setting the loudness compensation of Output Channel 2 to ON

ABH, 03H, 01H, 01H, 01H

5.9. Filter Settings

Perform Filter (HPF/LPF) settings of Input / Output channels. 9000M2 Series Amplifier responds with the same data as the receipt.

Note: Command cannot be received during power off.

A2H, 04H, <Channel Attribute>, <Channel Number>, <HPF/LPF>, < Frequency Value>

<Channel Attribute>

00H: Input channel 01H: Output channel

<Channel Number>

00H - 07H (Input channel 1 - 8) 00H - 07H (Output channel 1 - 8)

<HPF/LPF>

00H: High Pass Filter 01H: Low Pass Filter

<Frequency Value>

HIGH PASS FILTER TABLE – 00H

| Va | lue | Freq | Va | lue | Freq |
|-----|-----|------|-----|-----|-------|
| HEX | DEC | (Hz) | HEX | DEC | (Hz) |
| 00H | 0 | OFF | 11H | 13 | 800 |
| 01H | 1 | 20 | 12H | 14 | 1k |
| 02H | 2 | 25 | 13H | 15 | 1.25k |
| 03H | 3 | 31.5 | 14H | 16 | 1.6k |
| 04H | 4 | 40 | 15H | 17 | 2k |
| 05H | 5 | 50 | 16H | 18 | 2.5k |
| 06H | 6 | 63 | 17H | 19 | 3.15k |
| 07H | 7 | 80 | 18H | 20 | 4k |
| 08H | 8 | 100 | 19H | 21 | 5k |
| 09H | 9 | 125 | 1AH | 22 | 6.3k |
| 0AH | 10 | 160 | 1BH | 23 | 8k |
| 0BH | 11 | 200 | 1CH | 24 | 10k |
| 0CH | 12 | 250 | 1DH | 25 | 12.5k |
| 0DH | 13 | 315 | 1EH | 26 | 16k |
| 0EH | 14 | 400 | 1FH | 27 | 20k |
| 0FH | 15 | 500 | | | |
| 10H | 16 | 630 | | | |

LOW PASS FILTER TABLE – 01H

| Va | lue | Freq | Va | lue | Freq |
|-----|-----|------|-----|-----|-------|
| HEX | DEC | | HEX | DEC | |
| 00H | 0 | 20 | 11H | 13 | 1k |
| 01H | 1 | 25 | 12H | 14 | 1.25k |
| 02H | 2 | 31.5 | 13H | 15 | 1.6k |
| 03H | 3 | 40 | 14H | 16 | 2k |
| 04H | 4 | 50 | 15H | 17 | 2.5k |
| 05H | 5 | 63 | 16H | 18 | 3.15k |
| 06H | 6 | 80 | 17H | 19 | 4k |
| 07H | 7 | 100 | 18H | 20 | 5k |
| 08H | 8 | 125 | 19H | 21 | 6.3k |
| 09H | 9 | 160 | 1AH | 22 | 8k |
| 0AH | 10 | 200 | 1BH | 23 | 10k |
| 0BH | 11 | 250 | 1CH | 24 | 12.5k |
| 0CH | 12 | 315 | 1DH | 25 | 16k |
| 0DH | 13 | 400 | 1EH | 26 | 20k |
| 0EH | 14 | 500 | 1FH | 27 | OFF |
| 0FH | 15 | 630 | | | |
| 10H | 16 | 800 | | | |

Example: Setting the Input Channel 3's High Pass Filter to 31.5 Hz. A2H, 04H, 00H, 02H, 00H, 03H

5.10. Input Sensitivity Setting

Performs input sensitivity setting of Input channel. 9000M2 Series Amplifier responds with the same data as that received. Input sensitivity setting is enabled only for the channel on which the D-001T or AN-001T is used.

Note: Command cannot be received during power off.

ACH, 02H, <Channel Number>, <Value>

<Channel Number>
00H - 07H (Input channel 1 - 8)

<Value >

INPUT SENSITIVITY TABLE

| Va | lue | Sense | Value | | Sense |
|-----|-----|-------|-------|-----|-------|
| HEX | DEC | (dB) | HEX | DEC | (dB) |
| 00H | 0 | -10 | 05H | 5 | -42 |
| 01H | 1 | -18 | 06H | 6 | -48 |
| 02H | 2 | -24 | 07H | 7 | -54 |
| 03H | 3 | -30 | 08H | 8 | -60 |
| 04H | 4 | -36 | | | |

Example: Setting the input sensitivity of Input Channel 5 to –24 dB. ACH, 02H, 04H, 02H

5.11. Phantom Power ON/OFF Setting

Sets the phantom power of Input channel to ON or OFF. 9000M2 Series Amplifier responds with the same data as that received.

Note: Command cannot be received during power off.

87H, 02H, <Channel Number>, <OFF/ON>

<Channel Number>
00H - 07H (Input channel 1 - 8)

<OFF/ON>

00H: PHANTOM OFF 01H: PHANTOM ON

Example: Setting the phantom power of Input Channel 1 to ON.

87H, 02H, 00H, 01H

5.12. Paging Event Preset Recall

Activates or terminates paging event.

Note: Command cannot be received during power off.

F2H,02H, <Paging Event No>, <Control>

< Paging Event No > 00H – 1FH (Paging Event 1 - 32)

<Control>

00H: Stop 01H: Start

Example: Activating paging event 1. F2H, 02H, 00H, 01H

6. Channel Name Request

Reads input and output channels' names. The 9000M2 Series Amplifier responds with the channel name to this command.

F0H, 03H, 40H, <Channel Attribute>, <Channel Number>

<Channel Attribute>

00H: Input channel 01H: Output channel

<Channel Number>

00H - 07H (Input channel 1 - 8) 00H - 07H (Output channel 1 - 8)

Example: Acquiring the Input Channel 1's name.

F0H, 03H, 40H, 00H, 00H

Response data are provided below.

COH, 09H, <Channel Attribute>, <Channel Number>,

<aSCII Data (1byte)>, <aSCII Data (2byte)>, <aSCII Data (3byte)>,

<aSCII Data (4byte)>, <aSCII Data (5byte)>, <aSCII Data (6byte)>,

<ASCII Date (7byte)>

Example: Responding with the Input Channel 1's name "INPUT1." C0H, 09H, 00H, 00H, 49H, 4EH, 50H, 55H, 54H, 31H, 00H

Table below shows ASCII codes used for Names.

| Numeric | 0 | 1 | 2 | 3 | 4 | 5 | 6 | 7 | 8 | 9 |
|------------|-----|-----|-----|-----|-----|-----|-----|-----|-----|-----|
| | 30H | 31H | 32H | 33H | 34H | 35H | 36H | 37H | 38H | 39H |
| Alphabetic | Α | В | С | D | Е | F | G | Н | 1 | J |
| | 41H | 42H | 43H | 44H | 45H | 46H | 47H | 48H | 49H | 4AH |
| | K | L | М | N | 0 | Р | Q | R | S | Т |
| | 4BH | 4CH | 4DH | 4EH | 4FH | 50H | 51H | 52H | 53H | 54H |
| | U | V | W | Х | Y | Z | | | | |
| | 55H | 56H | 57H | 58H | 59H | 5AH | | | | |
| Symbol | " | \$ | & | > | (|) | * | + | - | 1 |
| | 22H | 24H | 26H | 27H | 28H | 29H | 2AH | 2BH | 2DH | 2FH |
| | < | = | > | ? | [| ¥ |] | _ | | |
| | 3CH | 3DH | 3EH | 3FH | 5BH | 5CH | 5DH | 5FH | | |

7. Speaker Preset Setting

Recalls speaker EQ preset values for specific TOA model speakers. 9000M2Series Amplifier responds with the same data as that received.

Note: Command cannot be received during power off.

ADH, 02H, <Output Channel Number>, <Value>

<Output Channel Number>
00H - 07H (Output channel 1 - 8)

<Value >

SPEAKER PRESET TABLE

| Va | lue | Sense (dB) | Vá | alue | Sense (dB) |
|-----|-----|--------------|-----|------|---------------|
| HEX | DEC | | HEX | DEC | |
| 00H | 0 | ALL FLAT | 10H | 16 | F-1522 |
| 01H | 1 | F-122 | 11H | 17 | FB-2322 |
| 02H | 2 | F-122 LOWCUT | 12H | 18 | FB-2352 |
| 03H | 3 | H-1 | 13H | 19 | FB-2852 |
| 04H | 4 | H-1 LOWCUT | 14H | 20 | SR-H2S |
| 05H | 5 | H-2 | 15H | 21 | SR-H2L |
| 06H | 6 | H-2 LOWCUT | 16H | 22 | SR-H3S |
| 07H | 7 | H-3 | 17H | 23 | SR-H3L |
| 08H | 8 | H-3 LOWCUT | 18H | 24 | HS-120 |
| 09H | 9 | HB-1 | 19H | 25 | HS-150 |
| 0AH | 10 | FB-100 | 1AH | 26 | HS-1200 |
| 0BH | 11 | SW FOR F-122 | 1BH | 27 | HS-1500 |
| 0CH | 12 | SR-S4 | 1CH | 28 | F-1000 LOWCUT |
| 0DH | 13 | HX-5 | 1DH | 29 | F-1300 LOWCUT |
| 0EH | 14 | HX-5_LOWCUT | 1EH | 30 | F-2000 LOWCUT |
| 0FH | 15 | FB-120 | | | |

8. ANC ADJUST

8.1. ANC Adjust Setting

Adjusts reference level of sensing ambient noise variation.

AEH, 02H, < Channel Number > < Adjust Value >

<Channel Number>
00H - 07H (AN channel 1 - 8)
<Adjust Value>
Value
00 - 14H (-10dB to 10dB)
See Adjust Value Table on the next page

Example: Setting reference level of channel 1 to –9dB.

AEH, 02H, 00H, 01H

Response data are provided below.

C1H, 01H, <OK/NG>

00H:OK 01H:NG

ANC Adjust Value Table

| ANC | Aujusi | value l'able |
|-----|--------|--------------|
| Va | lue | Value (dB) |
| HEX | DEC | |
| 00H | 0 | -10dB |
| 01H | 1 | -9dB |
| 02H | 2 | -8dB |
| 03H | 3 | -7dB |
| 04H | 4 | -6dB |
| 05H | 5 | -5dB |
| 06H | 6 | -4dB |
| 07H | 7 | -3dB |
| 08H | 8 | -2dB |
| 09H | 9 | -1dB |
| 0AH | 10 | 0dB |
| 0BH | 11 | 1dB |
| 0CH | 12 | 2dB |
| 0DH | 13 | 3dB |
| 0EH | 14 | 4dB |
| 0FH | 15 | 5dB |
| 10H | 16 | 6dB |
| 11H | 17 | 7dB |
| 12H | 18 | 8dB |
| 13H | 19 | 9dB |
| 14H | 10 | 10dB |

8.2. ANC Get Reference

Reads current reference level of ANC.

F3H, 01H, < Channel Number>

<Channel Number>
00H - 07H (AN channel 1 - 8)

See Reference Level Table on the next page

Example: Acquiring reference level of channel 1.

F3H, 01H, 00H

Response data are provided below.

C2H, 01H, <Ref Level>

00H:OK 01H:NG

Reference Level Value Table

| va | lue | Gain | Va | lue | Gain | Va | lue | Gain |
|-----|-----|------|-----|-----|------|-----|-----|------|
| HEX | DEC | (dB) | HEX | DEC | (dB) | HEX | DEC | (dB) |
| 00h | 0 | -50 | 20h | 32 | -18 | 40h | 64 | +14 |
| 01h | 1 | -49 | 21h | 33 | -17 | 41h | 65 | +15 |
| 02h | 2 | -48 | 22h | 34 | -16 | 42h | 66 | +16 |
| 03h | 3 | -47 | 23h | 35 | -15 | 43h | 67 | +17 |
| 04h | 4 | -46 | 24h | 36 | -14 | 44h | 68 | +18 |
| 05h | 5 | -45 | 25h | 37 | -13 | 45h | 69 | +19 |
| 06h | 6 | -44 | 26h | 38 | -12 | 46h | 70 | +20 |
| 07h | 7 | -43 | 27h | 39 | -11 | 47h | 71 | +21 |
| 08h | 8 | -42 | 28h | 40 | -10 | 48h | 72 | +22 |
| 09h | 9 | -41 | 29h | 41 | -9 | 49h | 73 | +23 |
| 0Ah | 10 | -40 | 2Ah | 42 | -8 | 4Ah | 74 | +24 |
| 0Bh | 11 | -39 | 2Bh | 43 | -7 | 4Bh | 75 | +25 |
| 0Ch | 12 | -38 | 2Ch | 44 | -6 | 4Ch | 76 | +26 |
| 0Dh | 13 | -37 | 2Dh | 45 | -5 | 4Dh | 77 | +27 |
| 0Eh | 14 | -36 | 2Eh | 46 | -4 | 4Eh | 78 | +28 |
| 0Fh | 15 | -35 | 2Fh | 47 | -3 | 4Fh | 79 | +29 |
| 10h | 16 | -34 | 30h | 48 | -2 | 50h | 80 | +30 |
| 11h | 17 | -33 | 31h | 49 | -1 | 51h | 81 | +31 |
| 12h | 18 | -32 | 32h | 50 | 0 | 52h | 82 | +32 |
| 13h | 19 | -31 | 33h | 51 | +1 | 53h | 83 | +33 |
| 14h | 20 | -30 | 34h | 52 | +2 | 54h | 84 | +34 |
| 15h | 21 | -29 | 35h | 53 | +3 | 55h | 85 | +35 |
| 16h | 22 | -28 | 36h | 54 | +4 | 56h | 86 | +36 |
| 17h | 23 | -27 | 37h | 55 | +5 | 57h | 87 | +37 |
| 18h | 24 | -26 | 38h | 56 | +6 | 58h | 88 | +38 |
| 19h | 25 | -25 | 39h | 57 | +7 | 59h | 89 | +39 |
| 1Ah | 26 | -24 | 3Ah | 58 | +8 | 5Ah | 90 | +40 |
| 1Bh | 27 | -23 | 3Bh | 59 | +9 | 5Bh | 91 | +41 |
| 1Ch | 28 | -22 | 3Ch | 60 | +10 | 5Ch | 92 | +42 |
| 1Dh | 29 | -21 | 3Dh | 61 | +11 | | | |
| 1Eh | 30 | -20 | 3Eh | 62 | +12 | | | |
| 1Fh | 31 | -19 | 3Fh | 63 | +13 | | | |

9. COMMAND LIST

| Function | Command Code |
|---|---|
| Channel fader gain | 91H, 03H, <channel attribute="">, <channel number="">, <value> (position)</value></channel></channel> |
| | 96H, 03H, <channel attribute="">, <channel number="">, <value> (position)</value></channel></channel> |
| | 93H, 03H, <channel attribute="">, <channel number="">, <value> (step)</value></channel></channel> |
| Crosspoint gain | 95H, 05H, <source attribute="" channel=""/> , <source channel="" number=""/> , <destination attribute="" channel="">, <destination channel="" number="">, <value></value></destination></destination> |
| Preset memory recall | F1H, 02H, 00H, <preset number=""></preset> |
| Terminate "EVENT" | F1H, 02H, 01H, <event number=""></event> |
| Channel ON/OFF | 92H, 03H, <channel attribute="">, <channel number="">, <off on=""></off></channel></channel> |
| Power ON/OFF | F4H, 01H, <on off=""></on> |
| Tone control (BASS/TREBLE) | AAH, 04H, <channel attribute="">, <channel number="">, <bass treble="">, <value></value></bass></channel></channel> |
| EQ settings - ON/OFF setting - Band No, setting - Gain setting - Q setting - Center frequency setting | A1H, 07H, <channel attribute="">, <channel number="">, <off on="">,<band number="">, <gain value="">, <q value="">, <freq value=""></freq></q></gain></band></off></channel></channel> |
| Loudness compensation | ABH, 03H, <channel attribute="">, <channel number="">, <off on=""></off></channel></channel> |
| Filter setting - HPF setting - LPF setting | A2H, 04H, <channel attribute="">, <channel number="">, <hpf lpf="">, <value></value></hpf></channel></channel> |
| Input sensitivity setting | ACH, 02H, <channel number="">, <value>: (Input channel only)</value></channel> |
| Phantom power setting | 87H, 02H, <channel number="">, <off on="">: (Input channel only)</off></channel> |
| Paging Event
Preset Recall | F2H,02H, <paging event="" no="">, <control></control></paging> |
| Channel name request | F0H, 03H, 40H, <channel attribute="">, <channel number=""></channel></channel> |
| | [Response code] C0H, 09H, <channel attribute="">, <channel number="">, <ascii data(1byte)="">, <ascii data(2byte)="">, <ascii< td=""></ascii<></ascii></ascii></channel></channel> |
| | Data(3byte)>,
<ascii data(4byte)="">, <ascii data(5byte)="">, <ascii
Data(6byte)>,
<ascii data(7byte)=""></ascii></ascii
</ascii></ascii> |

| ANC Adjust | AEH, 02H, <channel number=""><adjust value=""></adjust></channel> |
|---------------|---|
| Setting | |
| ANC Reference | F3H, 01H, , <channel number=""></channel> |

10. COMMUNICATION EXAMPLES

| Command | Controller | 9000M2 Response | | | | |
|---|-------------------------------|--------------------------------------|--|--|--|--|
| Channel fader gain | | | | | | |
| Input ch1 Fader gain=0dB | 91H, 03H, 00H, 00H, 6AH | 91H, 03H, 00H, 00H, 6AH | | | | |
| Input ch1 Fader gain 1 step | 93H, 03H, 00H, 00H, 41H | 93H, 03H, 00H, 00H, 6CH | | | | |
| up | | (Amplifier response of +1dB Input | | | | |
| | | Channel 1 fader gain after command.) | | | | |
| | | - | | | | |
| Output ch1 Fader gain=-∞dB | 91H, 03H, 01H, 00H, 00H | 91H, 03H, 01H, 00H, 00H | | | | |
| Paing Output ch1 Fader | 96H,03H,01H,01H,6AH | 96H,03H,01H,01H,6AH | | | | |
| gain=0dB | | | | | | |
| | Crosspoint gain | | | | | |
| Input ch1->Output ch1 0dB | 95H, 05H, 00H, 00H, 01H, 00H, | 95H, 05H, 00H, 00H, 01H, 00H, | | | | |
| | 47H | 47H | | | | |
| Input ch3->Output ch5 -20dB | 95H, 05H, 00H, 02H, 01H, 04H, | 95H, 05H, 00H, 02H, 01H, 04H, | | | | |
| | 33H | 33H | | | | |
| Input ch4->Output ch1 1 step | 95H, 05H, 00H, 03H, 01H, 00H, | 95H, 05H, 00H, 03H, 01H, 00H, | | | | |
| up | 70H | 70H | | | | |
| Fronts Otart (Matrix) | Preset memory recall | E411 0011 0011 | | | | |
| Event1 Start (Matrix) | F1H, 02H, 00H, 00H | F1H, 02H, 00H, 00H | | | | |
| Scene5 Load (Mixer) | F1H, 02H, 00H, 04H | F1H, 02H, 00H, 04H | | | | |
| Touris de Francis (Matrix) | Terminate "EVENT" (Matrix) | E411 0011 0411 0011 | | | | |
| Terminate Event1 (Matrix) F1H, 02H, 01H, 00H F1H, 02H, 01H, 00H | | | | | | |
| Least and OFF | Channel ON/OFF | 0011 0011 0011 0011 | | | | |
| Input ch1 OFF | 92H, 03H, 00H, 00H, 00H | 92H, 03H, 00H, 00H, 00H | | | | |
| Output ch2 ON | 92H, 03H, 01H, 01H, 01H | 92H, 03H, 01H, 01H | | | | |
| Device OFF | Power ON/OFF | E411 0411 0011 | | | | |
| Power OFF | F4H, 01H, 00H | F4H, 01H, 00H | | | | |
| Power ON | F4H, 01H, 01H | F4H, 01H, 01H | | | | |
| Location December 54D | Tone control (Bass/Treble) | AALL 04LL 00LL 00LL 07LL | | | | |
| Input ch1 Bass gain -5dB | AAH, 04H, 00H, 00H, 00H, 07H | AAH, 04H, 00H, 00H, 00H, 07H | | | | |
| Output ch3 Treble gain 0dB | AAH, 04H, 01H, 02H, 01H, 0CH | AAH, 04H, 01H, 02H, 01H, 0CH | | | | |
| Input ch2 Treble gain 2 step | AAH, 04H, 00H, 01H, 01H, 2EH | AAH, 04H, 00H, 01H, 01H, 2EH | | | | |
| up | | | | | | |
| Output ch1 Bass gain 1 step | AAH, 04H, 01H, 00H, 00H, 21H | AAH, 04H, 01H, 00H, 00H, 21H | | | | |
| down | | | | | | |
| EQ setting | | | | | | |
| Input ch1 EQ ON, Band01, | A1H, 07H, 00H, 00H, 01H, 00H, | A1H, 07H, 00H, 00H, 01H, 00H, | | | | |
| Gain +1dB, Q 0.5, Freq 40Hz | 0DH, 01H, 03H | 0DH, 01H, 03H | | | | |
| Output ch3 EQ ON, Band05, | A1H, 07H, 01H, 02H, 01H, 04H, | A1H, 07H, 01H, 02H, 01H, 04H, | | | | |
| Gain 0dB, Q 3, Freq 200Hz | OCH, 06H, 0AH | 0CH, 06H, 0AH | | | | |
| Loudness compensation settings | | | | | | |
| Input ch4 Loudness ON | ABH, 03H, 00H, 03H, 01H | ABH, 03H, 00H, 03H, 01H | | | | |
| Filter settings | | | | | | |

| Input ch2 Hpf 31.5Hz | A2H, 04H, 00H, 01H, 00H, 03H | A2H, 04H, 00H, 01H, 00H, 03H | | | | |
|------------------------------|------------------------------|------------------------------|--|--|--|--|
| Output ch1 Lpf 6.3kHz | A2H, 04H, 01H, 00H, 01H, 02H | A2H, 04H, 01H, 00H, 01H, 02H | | | | |
| Command | Controller | 9000M2 Response | | | | |
| | Input sensitivity setting | | | | | |
| Input ch1 Insense -24dB | ACH, 02H, 00H, 02H | ACH, 02H, 00H, 02H | | | | |
| | Speaker preset setting | | | | | |
| Output ch2 SpPreset F-122 | ADH, 02H, 01H, 01H | ADH, 02H, 01H, 01H | | | | |
| | Phantom power setting | | | | | |
| Input ch3 Phantom ON | 87H, 02H, 02H, 01H | 87H, 02H, 02H, 01H | | | | |
| | Paging Event Preset Recall | | | | | |
| Paging No1 Activates | F2H,02H,00H,01 | F2H,02H,00H,01 | | | | |
| | Channel name recall | | | | | |
| Input ch1 Name "INPUT1" | F0H, 03H, 40H, 00H, 00H | C0H, 09H, 00H, 00H, | | | | |
| | | 49H, 4EH, 50H, | | | | |
| | | 55H, 54H, 31H, 00H | | | | |
| | ANC ADJUST | | | | | |
| Reference Level Of Ch1 to | AEH,02H,00H,01H | C1H,01H,00H | | | | |
| –9dB | | | | | | |
| | ANC Get Reference | | | | | |
| Acquiring reference level of | F3H,01H,00h | C2H,01H,32H(0dB) | | | | |
| Ch1 | | | | | | |